

From tinySA

Main: USB Interface

After connecting the tinySA to a PC using the a USB cable a serial interface will become available on the PC. Drivers for the serial interface over USB will be automatically installed on Windows and are already builtin in most Linux kernels The serial interface supports a large set of commands. You can always use the **help** command to get a list of the available commands

There is limited error checking against incorrect parameters of incorrect mode

- Frequencies can be specified using an integer optionally postfixed with a the letter 'k' for kilo 'M' for Mega or 'G' for Giga. E.g. 0.1M (100kHz), 500k (0.5MHz) or 12000000 (12MHz)
- Levels are specified in dB(m) and can be specified using a floating point notation. E.g. 10 or 2.5
- Time is specified in seconds optionally postfixed with the letters 'm' for mili or 'u' for micro. E.g. 1 (1 second), 2.5 (2.5 seconds), 120m (120 milliseconds)

Commands:

attenuate

sets the internal attenuation to automatic or a specific value
usage: attenuate [auto|0-31]

abort

enables the previous command abortion of aborts the previous command
usage: abort [off|on]

When used without parameters the previous command still running will be aborted. Abort must be enabled before usage using the "abort on" command

bulk

send by tinySA when in auto refresh mode

format: "bulk\r\n{X}{Y}{Width}{Height}{Pixeldata}\r\n"

where all numbers are binary coded 2 bytes little endian. The Pixeldata is encoded as 2 bytes per pixel

calc

sets or cancels one of the measurement modes

usage: calc off|min|hl|max|hl|max|dl|aver4|aver16|quasip

the commands are the same as those listed in the MEASURE menu

caloutput

disables or sets the caloutput to a specified frequency in MHz

usage: caloutput off|30|15|10|4|3|2|1

capture

requests a screen dump to be send in binary format of 320x240 pixels of each 2 bytes

clearconfig

resets the configuration data to factory defaults

usage: clearconfig 1234

color

sets or dumps the colors used

usage: color [{id} {rgb24}]

correction

sets or dumps the frequency level correction table

usage: correction {table_name} [(0..9|0..19) {frequency} {level}]

dac

sets or dumps the dac value

usage: dac [0..4095]

data

dumps the trace data

usage: data 0..2

0=temp value, 1=stored trace, 2=measurement

deviceid

sets or dumps a user settable number that can be use to identify a specific tinySA

usage: deviceid [{number}]

fill

send by tinySA when in auto refresh mode

format: "fill\r\n{X}{Y}{Width}{Height}{Color}\r\n"

where all numbers are binary coded 2 bytes little endian.

freq

pauses the sweep and sets the measurement frequency

usage: freq {frequency}

frequencies

dumps the frequencies used by the last sweep

usage: frequencies

if

sets the IF to automatic or a specific value

usage: if (0 | 433M..435M)

where 0 means automatic

info

displays various SW and HW information

help

dumps a list of the available commands

usage: help

hop (Ultra only)

measures the input level at each of the requested frequencies

usage: hop {start(Hz)} {stop(Hz)} {step(Hz) | points} [outmask]

If the 3rd parameter is below 450 it is assumed to be points, otherwise as step frequency

Outmask selects if the frequency (1) or level (2) is output.

level

sets the output level

usage: level -76..13

Not all values in the range are available

levelchange

sets the output level delta for low output mode level sweep

usage: levelchange -70..+70

leveloffset

sets or dumps the level calibration data

usage: leveloffset low|high|switch [output] {error}

For the output corrections first ensure correct output levels at maximum output level. For the low output set the output to -50dBm and measure and correct the level with "leveloffset switch error" where

For all output leveloffset commands measure the level with the leveloffset to zero and calculate $\text{error} = \text{measured level} - \text{specified level}$

load

loads a previously stored preset

usage: load 0..4

where 0 is the startup preset

marker

sets or dumps marker info

usage: marker {id} on|off|peak|{freq}|{index}

where id=1..4 index=0..num_points-1

Marker levels will use the selected unit

Marker peak will activate the marker (if not done already), position the marker on the strongest signal and display the marker info

The frequency must be within the selected sweep range

menu

The menu command can be used to activate any menu item.

usage: menu {#} [{#}] [{#}] [{#}]

where # is the menu entry number starting with 1 at the top.

Example: menu 6 2 will toggle the waterfall option

mode

sets the mode of the tinySA

usage: mode low|high input|output

modulation

sets the modulation in output mode

usage: modulation off|AM_1kHz|AM_10Hz|NFM|WFM|extern

ext_gain

sets the external attenuation/amplification

usage: ext_gain -100..100

Works in both input and output mode

output

sets the output on or off

usage: output on|off

pause

pauses the sweeping in either input or output mode

usage: pause

rbw

sets the rbw to either automatic or a specific value

usage: rbw auto|3..600

the number specifies the target rbw in kHz

recall

same as load

refresh

enables/disables the auto refresh mode
Usage: refresh on|off

release

signals a removal of the touch
usage: release

remark

does nothing
usage: remark use any text

repeat

sets the number of measurements that should be taken at every frequency
usage: repeat 1..1000
increasing the repeat reduces the noise per frequency, repeat 1 is the normal scanning mode.

reset

resets the tinySA
usage: reset

restart

restarts the the tinySA after the specified number of seconds
usage: restart {seconds}
where 0 seconds stops the restarting.

resume

resumes the sweeping in either input or output mode
usage: resume

save

saves the current setting to a preset
usage: save 0..4
where 0 is the startup preset

saveconfig

saves the device configuration data
usage: saveconfig

scan

performs a scan and optionally outputs the measured data
usage: scan {start(Hz)} {stop(Hz)} [points] [outmask]
where the outmask is a binary OR of 1=frequencies, 2=measured data, 4=stored data and points is maximum 290

scanraw

performs a scan of unlimited amount of points and send the data in binary form
usage: scanraw {start(Hz)} {stop(Hz)} [points] [option]
The measured data is the level in dBm and is send as '{('x' MSB LSB)*points}'. To get the dBm level from the 16 bit data, divide by 32 and subtract 128 for the tinySA and 174 for the tinySA Ultra.
The option, when present, can be either 0,1,2 or 3 being the sum of 1=unbuffered and 2=continuous

selftest

performs one or all selftests
usage: selftest 0 0..9

spur
enables or disables spur reduction
usage: spur on|off

sweep
set sweep boundaries or execute a sweep
usage: sweep [(start|stop|center|span|cw {frequency}) | ({start(Hz)} {stop(Hz)} [0..290])]
sweep without arguments lists the current sweep settings, the frequencies specified should be within the permissible range. The sweep commands apply both to input and output modes

sweeptime
sets the sweeptime
usage: sweep {time(Seconds)} the time specified may end in a letter where m=mili and u=micro

text
specifies the text entry for the active keypad
usage: text keypadtext
where keypadtext is the text used
Example: text 12M
Currently does not work for entering file names

threads
lists information of the threads in the tinySA

touch
sends the coordinates of a touch
usage: touch {X coordinate} {Y coordinate}
The upper left corner of the screen is "0 0"

touchcal
starts the touch calibration

touchtest
starts the touch test

trace
displays all or one trace information or sets trace related information
usage: trace [{0..2} | dBm|dBmV|dBuV|V|W |store|clear|subtract | (scale|ref|level) auto|{level}

trigger
sets the trigger type or level
usage: trigger auto|normal|single|{level(dBm)}
the trigger level is always set in dBm

vbat
displays the battery voltage

vbat_offset
displays or sets the battery offset value
usage: vbat_offset [{0..4095}]

version
displays the version text

wait

wait for a single sweep to finish and pauses sweep or waits for specified number of seconds

usage: wait [{seconds}]

waitscan

wait for the specified number of scans, or the current scan if not specified, to conclude and leaves the device in pause mode. All command execution will be clocked during waiting for the scans to complete

usage: waitscan [{scans}]

Retrieved from <https://tinysa.org/wiki/pmwiki.php?n=Main.USBInterface>

Page last modified on November 05, 2025, at 09:20 AM